

Installation MWIZ

1. Main

MOTIONWIZ



Windows XP

Windows 7

2. OS

2.1 windowsXP

windows XP

if during the installation there are problem of lost library:

- msvcp71.dll


- msucr71.dll

you can find this into the main root of motionwiz:

C:\Program Files (x86)\Parker\MotionWiz\Common\Help\Library for XP


How to registry the library:

- copy the file.dll into the directory: C:\windows\system32




- push start icon on the windows tool bar


- push execute command



- write: "regsvr32 msvc71.dll" and push enter



- write: "regsvr32 msvc71.dll" and push enter




- uninstall MotionWiz
- restart the PC
- install MotionWiz


2.2 windows7

WINDOWS 7

Before to run the exe file, push the right button and click on the "execute as administrator".



After, before to open the MotionWiz tools, open the property of the icon of the motionwiz (with the right button) and set the compatibility for XP and the set the execute as administrator:



P.S. the converter USBTODRIVE doesn't work with Windows 7 64bit, please install XPmode as virtual machine. We suggest the new converter USBTODRIVEN.